



VXML Interaction Server Configuration Guide Version 5.1.0

This page was not added to the PDF due to the following tag(s): article:topic-guide



VXML Interaction Server Requirements and Compatibility

Overview

This version of VIS is compatible with the following Virtual Hold components:

| VXML Interaction Server Version | Virtual Hold Version | Platform Toolkit Version | Open VXML Toolkit Library Version | Interactive Voice Gateway (IVG) | VIS Genesys IDriver for AVP/AEP |
|---------------------------------|----------------------|--------------------------|-----------------------------------|---------------------------------|---------------------------------|
| 5.1.0 | 8.0.6 | 4.0 | 5.1.0 | 1.0.0 | 2.0.1 |

Notes:

1. For information about other versions of Virtual Hold, refer to the *Legacy VXML Interaction Server Installation and Configuration Guide*.
2. For information about VIS Genesys IDriver for AVP and AEP, refer to the [VIS Genesys IDriver for AVP and AEP Release Notes](#).

VIS has been validated with the following Web servers:

- Apache Tomcat 6 and 7 (Windows only)
- Apache Tomcat 7 (Red Hat Enterprise Linux 6.5 only)
- WebLogic (10.3.6 only)
- Red Hat JBoss EAP 6.0

Media files may be stored separately from the VIS application. The following web servers have been validated for use as media servers:

- Apache Tomcat 6 and 7
- Microsoft IIS 6 and 7
- Apache HTTP Server 2.x
- Red Hat JBoss EAP 6.0

Configuring the VXML Interaction Server (toolkit.properties)

Overview

The configuration information for the VXML Interaction Server is stored in a `toolkit.properties` file. The `toolkit.properties` file contains settings that are used to determine routing decisions within the system. The following `toolkit.properties` template files are located in the `Sample_Configuration_x.x.x.xxx.zip` file for Version 5.1.0 on the VXML Interaction Server download location.

- `aacc.toolkit.properties`
- `avp.h323.toolkit.properties` (select this when H.323 inbound or outbound is used)
- `avp.sip.toolkit.properties` (select this when SIP inbound and outbound are used)
- `cic.toolkit.properties`
- `genesys.vxmlidriver.toolkit.properties`
- `gvp.toolkit.properties`
- `ivg.avaya.toolkit.properties`
- `ucce.toolkit.properties`
- `uccx.toolkit.properties`
- `voxeo.toolkit.properties`
- `vtop.toolkit.properties`

To configure the VXML Interaction Server, perform the following steps:

1. In Windows systems, create a `VirtualHold` folder on the same server and same drive that the Apache Tomcat Web server is installed on.
2. In Linux systems, create `/etc/VirtualHold` folder on the same server and same drive that the Apache Tomcat Web server is installed on.
3. Copy the appropriate `toolkit.properties` template file to the newly created `VirtualHold` folder.
4. Rename the template file to **`toolkit.properties`**.
5. Open the `toolkit.properties` file in a text editor.
6. Edit the file for your specific configuration based on the comments contained in the sample file.
7. **Save** and **Close** the file.

Optional: Changing Location of `toolkit.properties` File

If you want to store the file in a different location, you have two choices: create an environment variable, or configure the Apache Tomcat Web server to identify the new location. The default location is `C:/VirtualHold`.

For the environment variable, perform the following steps on the server that contains the VXML Interaction Server:

1. Right-click **My Computer** and select **Properties**.
2. (Windows 7) In the *System* window, click **Advanced system settings** in the left pane.
3. In the *System Properties* window, select the *Advanced* tab, then click **Environment Variables**
4. Under System Variables, click **New...** to add a new environment variable.
5. Enter the Variable name as **VHT_VIS_PATH**.
6. Enter the Variable value as the path to the toolkit.properties file.
7. Click **OK** twice, then close the *System* window.
8. Restart the server.

Or, on the server that contains Apache Tomcat, perform the following steps:

1. Open the **Apache Tomcat Java Properties** and select the Java tab.
2. Select the *Advanced* tab, then click **Environment Variables**
3. Enter the path to the toolkit.properties file in the Java Options text window.
4. Click **Apply**.

For Linux systems using Apache Tomcat:

1. Enter **/tomcat/bin** in command prompt.
2. Create a file named setenv.sh if not already done (refer [here](#) for more information).
3. Open the setenv.sh file.
4. Edit the file with a new location.
5. Put the toolkit.properties file in the location specified in the setenv.sh file.
6. Restart Apache Tomcat.

Refer to [Using JBoss EAP Web Server](#) for information about systems using JBoss EAP.

Configuring Toolkit.properties for External Media Files

Overview

The VXML Interaction Server can play voice prompts hosted on other media servers. These external media servers are configured in the toolkit.properties file.

Below is a sample toolkit.properties file for external media files.

Note: The external media settings are case insensitive.

Number of media servers: (external.mediaserver.count=1)

- When two or more media servers are used, change **external.mediaserver.count=1** to **external.mediaserver.count=X** (where X is the number of servers).

Path to each server: (external.mediaserver.1=http://[path to server])

- Change this to point to the directory where the voice files are stored on the first server.
- Add additional lines for **external.mediaserver.2**, etc. as needed (one line per server).

Note: Both HTTP and HTTPS are supported.

Balanced or failover mode: (external.mediaserver.distribution=)

- **balanced:** Individual prompts will be played from all media servers in a balanced fashion. (The distribution will be equally spread among all servers.)
- **failover:** All prompts will be played from the first server only. If the first server is not available, the second server in the list will be used. If the second is not available, the third will be used, and so on. (This setting is only effective if multiple servers are used.)

Note: Balanced mode will automatically handle a failover scenario. If one server fails, the other servers are used and the unavailable server is skipped.
In systems using Apache Tomcat, the Apache Tomcat log indicates which media servers are configured, but does not log the individual prompts. Prompts are logged in the browser log for GVP, CVP, or AVP (or other voice platform used). Both logs include the path to the server.

Failure log level: (external.mediaserver.logging=)

- **none:** A failure message will only be logged for the external media files if all servers fail.
- **first:** A failure message will only be logged for the first server to fail. Subsequent failures for that server are not logged. The other servers are logged upon start, but not fail.
- **all:** All possible success and failure messages will be logged.

Note: When using Apache Tomcat, refer to [Media Server Logging in Apache Tomcat](#) for sample log messages.



If this setting does not exist, the log level will default to "first".

Configuring Language and Custom Media Fields in EyeQueue

Overview

You must configure the Language and Custom Media fields in the **Adv Settings** ⇒ **Language Settings** section of EyeQueue for each segment to contain the correct language and custom folder name.

1. In the Select a Segment field, choose the segment.
2. Select the Language option, then enter the name for the language used by this segment exactly as shown here: Dutch, English, FrenchCanadian, SpanishNA or Mandarin Chinese.
3. Select the Custom Media option, then enter the folder name from the media server containing customized voice prompts for this segment.

Note: If the Custom Media value is blank or is not a valid folder name, the VXML Interaction Server will use the files from the Default folder for the specified language.
If the Language value is blank or is not a valid language name, the VXML Interaction Server will use the files from the Default folder for English.

4. Click **Submit**.

The language and custom media settings will take effect immediately. No restart of Virtual Hold is required.

Customizing External Media Files

Overview

Many clients use customized sets of voice prompts, instead of the standard voice files provided by Virtual Hold. The custom voice prompts must be organized using a specific folder structure so that the VXML Interaction Server will recognize them and play them correctly.

You can stage the voice files on any machine as you copy and arrange them. Then you will deploy the files to the media server(s).

You can use the Voices_x.x.x.xxx.zip file for Version 5.1.0 provided in the Virtual Hold Download Center as a starting point, or you can create a new parent folder to hold the voice files. This documentation assumes you are starting with the voices folder.

The voices (parent) folder must contain a subfolder for each language used. These folders must be named VHT_Dutch, VHT_English, VHT_FrenchCanadian, and/or VHT_SpanishNA. Each language folder must contain a subfolder named Default, and optionally extra subfolders containing custom files. The VXML Interaction Server will look for a custom voice file first. If a custom file cannot be found, it will use the files from the Default folder.

If you are using the voices folder from Virtual Hold with no changes, you can skip the steps below. Refer to the deployment steps listed in the [Deploying External Media Files](#) topic.

To set up custom prompts for VXML Interaction Server:

1. Navigate to the voices folder. Open the subfolder for the first language.
2. You will see a Default folder. This folder contains the standard set of voice prompts. We recommend making a copy of this folder under a different name (such as VHT_Defaults). This will preserve the files in case you need to use them later for troubleshooting.
3. Delete the contents of the Default folder and copy the files for the first custom call script here. Be sure this folder contains the full set of voice files.

Note: The Default folder must also contain these four additional files:

- .library
- ContactNumber.grxml
- ContactNumber.regex
- recordtone.wav

4. To set up a second call script, create a new folder (at the same level as Default) and copy the custom prompts for the second call script into it.
5. Repeat step 4 for the remaining call scripts.

Note: The new folders only need to contain those files which differ from the default. However, you may choose to copy entire prompt sets into the new folders. This will make the copying process simpler, but will result in more .wav files being stored on the media server(s).

Any major variation (such as male/female voice or US English/British English) must contain the full prompt set in its folder. It must also include blank .wav files to replace any files that are present in the default set that should not be played. This is to avoid mixing genders or languages. Refer to the **Sample Voice Project** below.

6. Make sure each subfolder under [first language] contains an empty .library file (size 0 KB). If needed, copy the .library file from the Default folder and paste it into the others.
7. Repeat steps 1-6 for other supported languages.
8. Deploy the voices folder and its contents to the media server(s). Refer to [Deploying External Media Files](#).
9. Configure EyeQueue to contain the correct language and custom folder name. Refer to [Configuring Language and Custom Media Fields in EyeQueue](#).

The changes will take effect immediately. No restart is needed.

Sample Voice Project

A client has six call scripts in English: four in US English and two in British English. The voice project should be set up in \voices\VHT_English as follows:

- The default set of US English prompts in "Default"
- Custom prompts only in US English in "VHTCallScript_2", "VHTCallScript_3", and "VHTCallScript_4"
- Full prompt sets in British English in "VHTCallScript_5" and "VHTCallScript_6"

If any prompt is missing from either 5 or 6, it will be played from "Default", which will be US English instead of British English.

Using JBoss EAP Web Server

Overview

This topic explains the procedures and configuration that must be performed in order for the VXML Interaction Server (VIS) to work with the JBoss EAP Web server:

- Deploying VXML Interaction Server .war File
- Creating Voices.war File
- Deploying Voices.war File
- Configuring Toolkit.properties File
- Changing Toolkit.properties File Location
- Changing VXML Interaction Server Log Level
- Verifying Log Functionality

Deploying VXML Interaction Server .war File

To deploy the correct VXM Interaction Server .war file:

1. Locate the VIS_x.x.x.xxx.war file within the unzipped VIS_x.x.x.xxx_JBOSS.zip file (for Version 5.1.0) results.
2. Open the JBoss Enterprise Application Platform application found at *jboss_server_ip_address:9990/console/App.html#deployments*.
3. Select **Runtime**.
4. Select **Manage Deployments**.

The screenshot shows the JBoss Enterprise Application Platform 6.0 interface. The top navigation bar includes 'Profile' and 'Runtime' tabs, with '(2) Messages' in the top right. A left sidebar contains a tree view with categories: Server, Configuration (with 'Manage Deployments' highlighted), Status, and Runtime Operations (with 'OSGi' selected). The main content area is titled 'Deployments' and contains the following elements:

- Deployments**: A section with the text: 'Currently deployed application components. Deployments that have been added through the filesystem will not be manageable through the web interface.'
- Available Deployments**: A section with a 'Filter:' input field and four buttons: 'Add', 'Remove', 'En/Disable', and 'Update'.
- Table**: A table with columns 'Name', 'Runtime Name', and 'Enabled'. The table body is empty, displaying 'No items!'.
- Selection**: Two input fields labeled 'Name:' and 'Runtime Name:'.

5. Click **Add**.
6. Click **Browse** in the Upload window.
7. Select the VIS_x.x.x.xxx.war file and click **Open**.
8. Click **Next**.
9. Enter the appropriate runtime name (with .war extension) of the VXML Interaction Server application in the Runtime Name field and click **Save**.

Note:

Do not change the Key and Name field values.

JBoss' ENTERPRISE APPLICATION PLATFORM 6.0 (4) Messages Profile Runtime

Server

Configuration

Manage Deployments

Status

JVM

Datasources

JPA

JNDI View

Transactions

Web

Webservices

Runtime Operations

OSGi

Deployments

Currently deployed application components. Deployments that have been added through the filesystem will not be manageable through the web interface.

Available Deployments

Filter:

Add Remove En/Disable Update

| Name | Runtime Name | Enabled |
|-------------------|--------------|--------------------------|
| VIS_x.x.x.xxx.war | VIS.war | <input type="checkbox"/> |

<< 1-1 of 1 >>

Selection

Name:

Runtime Name:

10. Select the VIS_x.x.x.xxx.war file and click **En/Disable** to enable the file.
11. Click **Confirm** when asked if the file should be enabled.
12. Verify the VIS_x.x.x.xxx.war file is deployed by using a Web browser to successfully navigate to the VXML Interaction Server application and confirm no errors are generated.

Creating Voices.war File

To create the voices.war file:

1. Copy the Voices_x.x.x.xxx.zip file (for Version 5.1.0) to a local directory.

Note:

Ensure the zip file does not contain a voices subdirectory!

2. Rename the Voices_x.x.x.xxx.zip file to voices.war.
3. Click **Yes** when asked to confirm the name change.

Deploying Voices.war File

To deploy the correct media files (voices.war file):

1. Locate the user created voices.war file.
2. Open the JBoss Enterprise Application Platform application found at *jboss_server_ip_address:9990/console/App.html#deployments*.
3. Select **Runtime**.
4. Select **Manage Deployments**.

JBoss Enterprise Application Platform 6.0

(4) Messages Profile Runtime

Server

Configuration

Manage Deployments

Status

JVM

Datasources

JPA

JNDI View

Transactions

Web

Webservices

Runtime Operations

OSGi

Deployments

Currently deployed application components. Deployments that have been added through the filesystem will not be manageable through the web interface.

Available Deployments

Filter:

Add Remove En/Disable Update

| Name | Runtime Name | Enabled |
|-------------------|--------------|-------------------------------------|
| VIS_x.x.x.xxx.war | VIS.war | <input checked="" type="checkbox"/> |

<< < 1-1 of 1 > >>

Selection

Name:

Runtime Name:

5. Click **Add**.
6. Click **Browse** in the Upload window.
7. Select the voices.war file and click **Open**.
8. Click **Next**.
9. Leave all field values unchanged and click **Save**.

JBoss Enterprise Application Platform 6.0 (1) Messages Profile Runtime

Server

Configuration

Manage Deployments

Status

JVM

Datasources

JPA

JNDI View

Transactions

Web

Webservices

Runtime Operations

OSGi

Deployments

Currently deployed application components. Deployments that have been added through the filesystem will not be manageable through the web interface.

Available Deployments

Filter:

| Name | Runtime Name | Enabled |
|-----------------|--------------|---------|
| VIS_x.x.xxx.war | VIS.war | ✓ |
| voices.war | voices.war | ⊘ |


<< 1-2 of 2 >>

Selection

Name:

Runtime Name:

10. Select the voices.war file and click **En/Disable** to enable the file.
11. Click **Confirm** when asked if the file should be enabled.



The screenshot shows the JBoss Enterprise Application Platform 6.0 interface. The top navigation bar includes 'Profile' and 'Runtime' tabs, with '(2) Messages' in the top right. The left sidebar contains a tree view with categories like 'Server', 'Configuration', 'Status', and 'Runtime Operations'. The main content area is titled 'Deployments' and shows a table of available deployments. The table has columns for 'Name', 'Runtime Name', and 'Enabled'. Two deployments are listed: 'VIS_x.x.x.xxx.war' and 'voices.war'. The 'voices.war' deployment is selected, and its details are shown in the 'Selection' section below the table, with 'Name' and 'Runtime Name' both set to 'voices.war'.

10. Verify the media files (in the voices.war file) are deployed:
 - a. Use a Web browser to navigate to `jboss_server_ip_address:8080/voices/vht_language_name`.
 - b. Verify all the media files for that language are listed.

Configuring Toolkit.properties File

To configure the toolkit.properties file:

1. Using a file browser, navigate to the JBoss EAP server.
2. Create and navigate to the `.../etc/VirtualHold` directory.
3. Copy the toolkit.properties file corresponding to your system type from the Sample_Configuration directory to the `.../etc/VirtualHold` directory.
4. Open the copied toolkit.properties file (refer to the following example).

```
# Sample configuration file for Genesys Voice Platform integrations
# URL for the Platform Toolkit web services
# Change the [PTK_server_address] and [PTK_port] to the address and port of the server where the Platform
# Toolkit software resides
# For example, http://10.10.0.158:7000/VHTPlatformWS-v4/
# Ensure the path and VHTPlatformWS version is correct by opening it in a web browser
com.virtualhold.toolkit.baseurl=http://[PTK_server_address]:[PTK_port]/VHTPlatformWS-v4/
```

```
# Setting to true causes details of Platform Toolkit requests and responses to be included in the web server logs
com.virtualhold.toolkit.debug=false
# Total number of media servers where voice files will be played from
external.mediaserver.count=1
# Media server url configuration
# This url is resolved by the voice browser so localhost will not work
# For additional entries, just increase the number on the end of the property name
# For example, external.mediaserver.2
external.mediaserver.1=http://[media_server_address]:[media_server_port]/voices/
# Distribution method options
# failover - Goes top to bottom attempting to fetch the media file and will play from the location where it first finds
the media file
# balanced - Load balances the media file fetching from the media servers, will failover if needed
external.mediaserver.distribution=failover
# Media server failure logging options
# none - will not log any media server failures
# first - will log the first time that a media server error occurs
# all - will log a media server error every time it occurs
external.mediaserver.logging=first
# Local path to the ASAP and Scheduled callback name files for recording
# Change the [web_server_install_directory] to the local path of the web server
# For example, C:/Program Files/Apache Software Foundation/Tomcat 6.0_Tomcat/webapps/ROOT
com.virtualhold.toolkit.audiopath=[web_server_install_directory]/webapps/ROOT
# Web path to the ASAP and Scheduled callback name files for playback
# Change the [web_server_address] and [web_server_port] to the URL and port of the web server
# For example, http://10.10.0.245:8080/
com.virtualhold.toolkit.webaudiopath=http://[web_server_address]:[web_server_port]/
# Used in day/time selection
# The ) and ] characters have unique properties when used to define the end of time group ranges
# For example, (12:00 am|6:00 am) includes times starting at 12:00 am through and including 6:00 am)
# For example, (12:00 am|6:00 am] includes times starting at 12:00 am through and including 5:59 am]
com.virtualhold.toolkit.earlymorning=(12:00 am|6:00 am]
com.virtualhold.toolkit.morning=(6:00 am|12:00 pm]
com.virtualhold.toolkit.afternoon=(12:00 pm|5:00 pm]
com.virtualhold.toolkit.evening=(5:00 pm|9:00 pm]
com.virtualhold.toolkit.night=(9:00 pm|11:59 pm]
# Default transfer destination during an inbound call, if destination cannot be retrieved from the Platform Toolkit
# Change the [default_transfer_destination] to the Genesys route point inbound calls should be transferred to if
calls default transfer from VIS to queue
# Enter the number of the route point, for example, 44333
com.virtualhold.toolkit.defaultdestination=[default_transfer_destination]
# Default transfer destination during an outbound call, if destination cannot be retrieved from the Platform Toolkit
# Change the [default_transfer_destination] to the Genesys route point outbound calls should be transferred to if
calls default transfer from VIS to queue
# Enter the number of the route point, for example, 44333
com.virtualhold.toolkit.outbound.defaultdestination=[default_transfer_destination]
# Inbound call routing control
# Determines whether VIS will control call routing or pass control back to an inbound URS routing strategy or
ORS workflow
# Set to true for GVP behind configuration
# VIS will return call to strategy/workflow when inbound treatment ends, strategy/workflow targets agent or
```



```
disconnects
# Set to False for GVP in front configuration
# VIS will send call to route point for queuing when inbound treatment ends or disconnects
# This property can be overridden with the URL query string parameter UseExternalRouting
com.virtualhold.toolkit.inbound.useexternalrouting=true
# Outbound call routing control
# Set to false when SSG is used to start the callback, call connected directly to VIS
# VIS sends to route point or disconnects when done
# Set to true when TMakePredictiveCall is used to start the callback (Queue mode PredictiveDial)
# Call goes to strategy/workflow which invokes VIS
# VIS returns call to strategy/workflow when done, strategy/workflow targets agent or disconnects
# This property can be overridden with the URL query string parameter UseExternalRouting
com.virtualhold.toolkit.outbound.useexternalrouting=false
```

5. Ensure the external media server is configured as follows:

```
external.mediaserver.1=http://10.10.3.41:8080/voices/
```

6. Ensure the URL for Platform Toolkit Web services is configured as follows:

```
com.virtualhold.toolkit.baseurl=http://ptk_server_ip_address/VHTPlatformWS-v4/
```

7. Ensure the name file configuration is set as follows:

```
com.virtualhold.toolkit.audiopath=/usr/local/jboss-eap-6.0/welcome-content/namefiles/
```

```
com.virtualhold.toolkit.webaudiopath=http://10.10.3.41:8080/namefiles/
```

8. Navigate to the welcome-content directory on the JBoss EAP server.
9. Create a subdirectory named **namefiles**.

Optional: Changing Location of Toolkit.properties File

To utilize a toolkit.properties file not located in the default location:

1. Open the JBoss Enterprise Application Platform application found at *jboss_server_ip_address:9990/console/App.html#deployments*.
2. Select **Profile**.
3. Select **System Properties**.

The screenshot shows the JBoss Enterprise Application Platform 6.0 configuration console. The top navigation bar includes "Profile" and "Runtime" tabs, with "(2) Messages" on the right. The left sidebar shows a tree view with "Profile" expanded, containing sub-items like Connector, JCA, Datasources, Resource Adapters, Mail, Container, Core, Infinispan, OSGi, Security, and Web. Below this is "General Configuration" with sub-items Interfaces, Socket Binding, and System Properties (highlighted). The main content area is titled "System Properties" and contains a table with columns "Key", "Value", and "Option". The table is currently empty, displaying "No items!". An "Add" button is located in the top right corner of the table area. Below the table, there are navigation controls showing "1-1 of 0" items.

4. Click **Add**.
5. Enter **VHT_VIS_PATH** in the Name field in the Create System Property window.
6. Enter the path to the directory containing the toolkit.properties file in the Value field.
7. Click **Save**.

The screenshot shows the JBoss Enterprise Application Platform 6.0 configuration console. The left sidebar contains a tree view with categories like Profile, Connector, Container, Core, Infinispan, OSGi, Security, Web, General Configuration, Interfaces, Socket Binding, and System Properties. The main area is titled 'System Properties' and contains a table with the following data:

| Key | Value | Option |
|--------------|-----------|--------|
| VHT_VIS_PATH | /usr/test | Remove |

There is an 'Add' button in the top right of the table area and pagination controls showing '1-1 of 1'.

Changing VXML Interaction Server Log Level

Temporary Change

To change the log level for a short time (for example, when troubleshooting), perform the following steps in a Web browser:


1. On the server where the VXML Interaction Server is installed, navigate to <http://server:port/warfile/-/logging>. The Current Log Level page is displayed.
2. Select the desired log level in the New Level field and click **Set**.
3. Change the level back when you are finished.

Note: The log level returns to the default setting when you restart the server or update the VXML Interaction Server application.

Permanent Change

To permanently change the default log level:

1. Open the JBoss Enterprise Application Platform application found at *jboss_server_ip_address:9990/console/App.html#deployments*.
2. Select **Profile**.
3. Select **System Properties**.




The screenshot shows the JBoss Enterprise Application Platform 6.0 console. The left sidebar contains a navigation menu with categories like Profile, Container, Core, Infinispan, OSGi, Security, Web, General Configuration, Interfaces, Socket Binding, and System Properties. The main content area is titled 'System Properties' and contains the following text: 'These properties are available throughout the configuration. The Boot-Time flag specifies if a property should be passed into the JVM start (-Dproperty=value)'. Below this is a table with columns 'Key', 'Value', and 'Option'. The table contains one row: 'VHT_VIS_PATH', '/usr/test', and 'Remove'. There is an 'Add' button and pagination '1-1 of 1'.

4. Click **Add**.
5. Enter **org.eclipse.vtp.loglevel** in the Name field in the Create System Property window.
6. Enter the desired log level in the Value field. Refer to the following table for more log level information.

| Log Level | Information Written to the Log |
|-----------|--------------------------------|
| ERROR | Errors |
| WARN | Errors and warnings |

| Log Level | Information Written to the Log |
|----------------|--|
| INFO (default) | Errors , warnings and informational output |
| DEBUG | Low level trace information |

7. Click **Save**.



The screenshot shows the JBoss Enterprise Application Platform 6.0 configuration console. The left sidebar contains a tree view with categories like Profile, Connector, Container, Core, Infinispan, OSGi, Security, Web, General Configuration, Interfaces, Socket Binding, and System Properties. The main area is titled 'System Properties' and contains a table of properties.

System Properties

These properties are available throughout the configuration. The Boot-Time flag specifies if a property should be passed into the JVM start (-Dproperty=value)

| Key | Value | Option |
|--------------------------|-----------|--------|
| VHT_VIS_PATH | /usr/test | Remove |
| org.eclipse.vtp.loglevel | ERROR | Remove |

Navigation: 1-2 of 2

Verifying Log Functionality

To verify the JBoss EAP server log exists and is functioning correctly:

1. Using a file browser, navigate to the JBoss server.
2. Open the `.../usr/local/jboss_eap-6.0/standalone/log/server.log` file and verify it contains application log entries.